TBMR

Cristie Bare Machine Recovery for TSM

User Guide

August 2010

Cristie Software Ltd
New Mill
Chestnut Lane
Stroud GL5 3EH
United Kingdom
Tel:+44(0)1453 847000
Fax:+44(0)1453 847001
cbmr@cristie.com

Cristie Data Products GmbH
Nordring 53-55

63843 Niedernberg
Germany
Tel: +49 (0) 60 28/97 95-0
Fax: +49 (0) 60 28/97 95 7-99
cbmr@cristie.de

Cristie Nordic AB
Gamla Värmdövägen 4

SE-131 37 Nacka
Sweden
Tel:+46(0)8 718 43 30
Fax:+46(0)8 718 53 40
cbmr@cristie.se

Copyright © 2003-2010 Cristie Software Ltd.
All rights reserved

The software contains proprietary information of Cristie Software Ltd; it is provided under a license agreement containing restrictions on use and disclosure and is also protected by copyright law. Reverse engineering of the software is prohibited.

Due to continued product development this information may change without notice. The information and intellectual property contained herein is confidential between Cristie Software Ltd and the client and remains the exclusive property of Cristie Software Ltd. If you find any problems in the documentation, please report them to us in writing. Cristie Software Ltd does not warrant that this document is error-free.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise without the prior written permission of Cristie Software Ltd.

IBM Tivoli Storage Manager (TSM) and TIVOLI are trademarks of the IBM Corporation.

PC-BaX, Cristie Storage Manager (CSM), SDB, TBMR (Bare Machine Recovery for TSM) and CBMR (Cristie Bare Machine Recovery) are trademarks of Cristie Software Ltd.

Cristie Software Ltd
New Mill
Chestnut Lane
Stroud
GL5 3EH
UK
+44 (0) 1453 847000
Internet E-Mail: cbmr@cristie.com
Website: http://www.cristie.com

Contents

1 Overview 2

1.1 Context 2
1.2 Prerequisites 2
1.3 Backup Process 2
1.4 Recovery Process 3

2 The TBMR Create Configuration Tool 4

2.1 Creating the Configuration Information 4

3 64-bit Versions of Windows XP, Vista, Windows 7, 2003 and 2008 6

4 Using a TSM Backup for Disaster Recovery 7

5 Encrypted Backups 8

6 Image Backups 10

7 Backupset Support 11

8 Restoring your System 12

8.1 Booting the DR Console 12
8.2 WinPE 2 Based TBMR Recovery Console 13
8.2.1 TBMR Recovery Console Main Menu 14
8.2.2 Start Automatic Recovery Wizard 15
8.2.3 Start Manual Recovery Sequence 27
8.3 Restore from Node 30
8.4 Restore from Backupset 30
8.4.1 Tools 39
8.4.2 Show Log and Error Reports 59
8.4.3 Copy Log and Error Report Files 60
8.4.4 Close Recovery Console and Reboot 60

9 Index 62

1 Overview

1.1 Context

This document describes the essential elements of TBMR and Disaster Recovery based upon a tailored WinPE recovery module. It is based upon version 6.3 of the software.

1.2 Prerequisites

An Intel x86, x64 or ia64 based processor, with 640MB RAM (1GB for Vista or later OS's) and 20MB free disk space running one of the following operating systems:

- Windows XP
- Windows 2003
- Windows Vista
- Windows 7
- Windows 2008
- Windows 2008 R2

Both 32 and 64-bit versions of XP, 2003, Vista, 7 and 2008 (including Core and R2) are supported. On Itanium (ia64) only Windows 2003, 2008 and 2008 R2 are supported.

TBMR requires a minimum TSM client version of 5.5.x.x on x86/x64/ia64. This must be installed and correctly configured prior to the installation of TBMR. Windows 2008 R2 requires a minimum client version of 6.1.2.0.

Ensure that either the BA Client Open File Support is installed and configured correctly. Select either LVSA or VSS as appropriate. This allows important OS files that are normally held open by the OS to be successfully backed up by TSM. TBMR will not successfully recover the OS without these files.

1.3 Backup Process

Cristie Bare Machine Recovery for IBM Tivoli (TBMR) allows you to perform a bare machine recovery of your system direct from an IBM Tivoli Storage Manager (TSM) backup.

To do this you must first prepare your system using the process outlined below.

1 Installation (refer to the TBMR Installation and Licensing Guide)
   - Install the TBMR configuration software
   - License the Software (using a Trial or Full license)Using a TSM Backup for Disaster Recovery (page 12, page 4, page 7)

2 Configuration
   - Save the Configuration parameters. Update when significant hardware changes are made.
   - Ensure that you have a bootable media (normally the WinPE DR CD-ROM).

3 Backup system and user data
   - Perform regular standard TSM backups (page 7) as required.

You will then be ready to *Restore the system from the Disaster Recovery Backup (page 12).*

1.4 Recovery Process

In the event of a disaster, having previously taken a TSM backup of the system and stored the configuration information, Windows PE mode DR enables you to restore your system to the state at the last TSM backup.

The TBMR recovery console is supplied on CD-ROM and if your machine supports bootable CD-ROMs (most PCs do) this is the most convenient way to boot the DR module. If the system does not support bootable CD-ROMs you can boot from the network. Contact Cristie for details on how to set this up.

Windows PE offers several advantages namely:

- a familiar Windows GUI
- the ability to inject new mass storage drivers during the boot process
- all variations of dynamic disks are supported (i.e. mirrored, spanned, striped and RAID-5)
- NTFS volumes/partitions are created natively
- support for NTFS mounted folders (junctions) and hard links
- the restored backup contains the original file security information

The WinPE recovery process has 5 main steps

1 Load Configuration data

2 Rebuild storage devices (hard disks)

3 Restore OS files from a TSM backup

4 Dissimilar Hardware (if necessary)

5 Boot into Windows

2 The TBMR Create Configuration Tool

Configuration information is saved by default to the *TBMRCFG* folder on the Windows system partition. This cannot be changed.

The Cristie tool that provides this function is called *TBMRCfg.exe* which is located in the TBMR installation folder (normally *Program Files \Cristie\TBMR*). This is a command line only tool which is licensed for use initially for a 30 day trial period. A full license is required to use the program beyond the trial period.

As part of this process, details about the hard disks, operating system, storage controller(s), network adapter(s) and network settings will be queried and stored. You can override some of these details if you wish.

The next sections discuss this process in more detail.

2.1 Creating the Configuration Information

To create the configuration manually run a command window and navigate to the folder where TBMR is installed. For example,



The TBMR configuration program is called TbmrCfg.exe. Enter the command `TbmrCfg.exe /?`. This will display the command line options available.


Command Prompt
C:\Program Files\Cristie\TBMR>TbmrCfg.exe /?
TBMR Configuration Utility Version 6.3
Copyright c 2009-2010 Cristie Software Limited
Usage: TBMRCFG.EXE [options]
Options are:
/help or /? - Show usage
/format <Drives to format|all> - Format additional volumes during recovery
Specify drives separated by comma as in /format D,E,F
For a volume that does not have a drive letter but mounted
under a folder, enter the mounted folder as in
/format D,D:\MountedVolume
/format all will format all partitions on all disks
The configuration will always be stored in %SystemDrive%\TBMRCFG
C:\Program Files\Cristie\TBMR>

The command line options are very simple:

/help or /?

Shows TbmrCfg usage. This displays the command option summary.

/format <Drives to format | all>

The `/format` option allows disk volumes other than the Windows drive to be formatted during the recovery. By default only the Windows volume will be formatted. There is an exception to this if Windows is not contained within the first partition of the disk. In that case both the Boot partition and the Windows partition will be configured for formatting. However, regardless of this setting, the WinPE based recovery environment will allow any or all partitions to be formatted.

So, for example, if volumes D:, E: and F: are to be additionally formatted during recovery, enter:

`TbmrCfg.exe /format D,E,F` (separate the drive letters using a comma)

Enter the following to back up all partitions on all drives on the system:

```
TbmrCfg.exe /format all
```

Volumes mounted on local folders not having a drive letter can be specified like this:

```
TbmrCfg.exe /format D:\MountedVolume
```

where `D:\MountedVolume` is the folder mount point. An example using both normal partitions and a mounted volume is:

```
TbmrCfg.exe /format D,D:\MountedVolume
```

TbmrCfg stores the configuration in `%SystemDrive%\TBMRCFG folder` (`%SystemDrive%` is the drive associated with the Windows folder, usually C:\). This location cannot be changed.

NOTE: It is important to remember that the TBMR configuration must be created before the BA Client backup is made. Cristie suggests that this is done by creating a job to run on the TSM Scheduler containing a script that calls the TbmrCfg.exe program installed in the TBMR installation folder.

3 64-bit Versions of Windows XP, Vista, Windows 7, 2003 and 2008

On these 64-bit OS's, files additional to the standard TSM backup dataset must be copied and saved. These include boot files and SystemState objects which are not normally backed up by the BA Client on these OS's.

Some of the additional files backed up are also locked at the time of backup and must be backed up using the Open File Manager VSS. So when TBMRCfg runs it invokes VSS to take a snapshot copy of these extra files (see below).


Command Prompt
C:\Program Files\Cristie\TBMR>TbmrCfg.exe
TBMR Configuration Utility Version 6.3 for x64
Copyright c 2009-2010 Cristie Software Limited
Copying the boot files ...
Created snapshot of C: --> E:
Successfully copied the boot files
Configuration was stored successfully
C:\Program Files\Cristie\TBMR>

4 Using a TSM Backup for Disaster Recovery

TBMR allows a previously created TSM backup or backupset to be used as a DR backup.

As long as the TBMR configuration has been created (see previous section) and a TSM backup is performed afterwards, then it will be possible to recover the system using the DR environment.

This document does not describe how to create TSM backups. Please refer to your TSM Administrator's Guide for details.

5 Encrypted Backups

TBMR supports encrypted TSM backups. This can be enabled in TSM by adding the line:

```
INCLUDE.ENCRYPT "*:\...\*"
```

to the dsm.opt file. TBMR works by creating the system configuration into the folder TBMRCFG. So the line above would mean that when the TSM backup is created, the TBMRCFG folder is also encrypted. This is not a problem though, but would mean that you will be prompted for the password during the recovery. If you wish to avoid this prompt add this additional line to dsm.opt `after` the line above:

```
EXCLUDE.ENCRYPT "*:\TBMRCFG\*"
```

You can also choose to always prompt for the encryption key password or have it stored locally. You will be prompted for the encryption key thus:

You should also select the appropriate encryption algorithm for your backup.

If the folder containing the TBMR configuration has been encrypted then during the recovery you will be prompted for the password:


TBMR Recovery Console
TBMR TSM Details
Please enter the TSM Server and Client details below and select [Next] to continue.
TSM Server Details
Password Request
Data is encrypted using a password. Enter the correct password and press [OK] to proceed. Pressing [Cancel] will abort the operation.
OK
Cancel
Wednesday, June 11, 2008
9:37:11 AM
< Back
Next >
Cancel
http://www.cristie.com

If the configuration folder has been excluded from the encryption (as described above) you will be prompted for the password during the '*Restore Files*' phase of the DR.

Please enter the same password you entered during the backup.

Note: If you have elected to have the password stored locally (via the BA Client Preferences menu) and the TBMR configuration has been created post this change, then you will not be prompted for the password during the recovery.

You may also need to perform a 'dummy' backup first to get the password stored locally before generating the TBMR configuration.

6 Image Backups

TBMR supports TSM backups of the form incremental, image and backupsets. However, for image backups, it is essential that in addition to the image backup, an incremental backup of the TBMRCFG folder is made to the same Node.

This is because it is not possible to retrieve the configuration details from an image backup.

If this extra incremental backup is not made then it will not be possible to perform a DR.

Note also that it is not possible to restore an image backup to a smaller disk partition

.

7 Backupset Support

TBMR now supports DR recovery from TSM backupsets. At the moment TBMR only supports *online* backupsets (i.e. those maintained in a Node on a TSM server). Typically a backupset is created with a dsmadmc command such as:

```
Generate Backupset <Nodename> <Prefix> Description="This is a
backupset test" Retention=Nolimit Wait=Yes Datatype=File TOC=Yes
DevClass=File
```

Where <Nodename> is the name of the node on the TSM server, <Prefix> is a short prefix to add to the backupset name.

Note that a backupset is created from a backup already present in the specified node. If this backup does not already contain a backup of the TBMRCFG folder generated by the TBMRCfg program, it will not be possible to recover the system from the backupset.

Note that it is essential to specify TOC=Yes. TBMR cannot recover a backupset created without a TOC (Table of Contents).

8 Restoring your System

If the situation arises where you need to recover your system, you have all the necessary information on the DR System CD, the DR Configuration Disk (or file) and the TSM Backup to get your system up and running in minimal time. The restore process requires little user intervention.

8.1 Booting the DR Console

Insert the bootable DR CD/DVD-ROM and reboot the machine. You will be prompted to *Press any key to boot from the CD or DVD*.

This prompt is only made for a few seconds before the system will attempt to boot the underlying OS, so you will need to react quickly!

8.2 WinPE 2 Based TBMR Recovery Console

When the WinPE 2 TBMR Console is booted, a Windows installation-like boot procedure is started.

During the boot process WinPE 2 drivers for your Plug and Play devices will be loaded - in particular the Mass Storage devices and Network Adapters. When the WinPE 2 system has booted it is possible to remove the CD if you wish.

Note that the DR Console will automatically reboot 72 hours after starting. This is an operating limitation of the Microsoft Windows PE 2 environment.

When this sequence completes the TBMR Recovery Console will be shown.

8.2.1 TBMR Recovery Console Main Menu

When you boot the WinPE 2 DR environment, you will see the TBMR Recovery Console Main Menu as below.


TBMR Recovery Console
Starts the automatic recovery wizard which will take you through the steps necessary to recover your system.
Starts the manual recovery wizard which will let you do individual recovery steps.
Lets you run various tools relevant to the recovery.
Shows a list of log and error report files from which individual ones can be selected for viewing in notepad.
Lets you copy all the log and error report files to a removable media or network location for support purposes.
Will close this console and reboot the system.
Set the timezone and time - 8/5/2010 11:58:14 AM
US
TBMR Recovery Console Version 6.3 Build 151
Copyright (C) 2006 - 2010 Cristie Software Limited
United Kingdom
http://www.cristie.com
cristie

You may configure the displayed date/time and the keyboard layout, by pressing the

icon.

By default the standard display uses US layout, but this may be changed to one of the listed alternatives. Select Date, Time and Time Zone to configure the locale.



8.2.2 Start Automatic Recovery Wizard

Select this option to commence a automatic DR sequence.


TBMR Recovery Console
TBMR - Welcome
Tivoli.
Welcome to the TBMR Recovery Wizard
This wizard will take you through the steps to fully recover your system from the saved configuration information and a recovery backup.
Select [Next] to proceed.
< Back
Next >
Cancel
United Kingdom
http://www.cristie.com
cristie

Press **Next>** to proceed to the first step of the sequence. Press **Cancel** to abort the recovery sequence at this point. You will then be presented with a dialog prompting you to select the type of the TSM restore.


TBMR - Select Restore Type
Please specify the type of restore you wish to perform:
Restore from a TSM node
Restore from a backupset stored on a TSM node
Restore from a backupset stored on a disk or removable media other than tape
< Back
Next >
Cancel

At the moment only restoring from a TSM node or an online backupset is supported. A future release will support restoring from a backupset stored on a disk or removable media. Make your choice and press **Next>** to continue.

Restore from Node

If you selected Restore from a node then select **Next>**. This will then display the Enter TSM server details as shown in the next section.

Specify TSM Details and Recovery Date/Time

The first step of the automatic recovery identifies the location of the TSM Server and Node used to back up the Client.



Selecting the Point-in-time (*PIT*) restore mode will allow the system to be recovered to a point closest to the specified date/time. The version of any files restored are closest to but not earlier than the specified date/time. If required to restore from an older date, selecting the down-arrow in the day/month field brings up a calendar.



This can be used to scroll the months/years backwards and forwards as necessary. Note, a future date will result in the latest backup being recovered.

If PIT mode is not selected then, by default, the latest file versions will be restored.Then select **Next>** to continue.

If the backup including the TBMR configuration folder TBMRCFG is encrypted, a prompt for the encryption password will be displayed if not held locally:


TBMR Recovery Console
TBMR TSM Details
Please enter the TSM Server and Client details below and select [Next] to continue.
TSM Server Details
Password Request
Data is encrypted using a password. Enter the correct password and press [OK] to proceed. Pressing [Cancel] will abort the operation.
OK
Cancel
Wednesday, June 11, 2008
9:37:11 AM
< Back
Next >
Cancel
http://www.cristie.com

Enter the password used during the backup.

Note: TBMR assumes that TCP/IP is the communication method used between the Client and the Server. Other TSM communication methods are not currently supported.

Press **OK>** to proceed.

Select Filespaces To Restore

The next step prompts for the filespaces to restore. Generally each filespace represents a disk partition or volume. Put a tick against each filespace that should be restored.



Note that the system and boot partitions (even if on different partitions) will always be restored by default.

Click **Next>** to continue to the next step.

Confirm Volume Layout

The next step in the automatic recovery shows a list of the disks and partitions to be recovered.


TBMR Recovery Console
TBMR - Volume Layout
The original and proposed disk volumes are shown below. If required, right-click on a volume to customise the proposed layout.
Stored layout:
Proposed layout:
VPC-WIN2K3R2
Disk 0 Size 15.99 GB []
Disk 1 Size 512 MB []
Disk 2 Size 512 MB []
Disk 3 Size 512 MB []
VPC-WIN2K3R2
Disk 0 Size 15.99 GB [VMwar
Disk 1 Size 509 MB [VMware,
Disk 2 Size 509 MB [VMware,
Disk 3 Size 509 MB [VMware,
Icon Help
< Back
Next >
Cancel
http://www.cristie.com

The left-hand panel of the display shows the original disk layout and partitions. The right-hand panel shows how the recovered disks will be partitioned after the recovery.

A green tick box next to a disk signifies that the disk and its underlying partitions will be left intact. Placed next to a partition/volume means that the corresponding partition/volume WILL NOT be partitioned.

A red exclamation mark placed next to a disk means it WILL be partitioned during recovery. Placed next to a partition or volume means that the corresponding partition/volume WILL be partitioned.

A red/white exclamation mark placed next to a disk means at least one partition/volume WILL be partitioned.

Click on the **Icon Help** button to display a summary of this:



When the recovery is to the original system the contents of both panels will look similar if the number of disks is the same. Possibly the disk sizes will be different (as in the above example).

When performing a recovery to a dissimilar system the disk mapping can be much more complex. Some of the criteria used to judge the disk mapping match are:

- disk geometry (tracks, cylinders and sectors)
- disk capacity
- if currently formatted, the disk signature

You may right-click on any disk shown in the right-hand panel to select whether the disk will be formatted or not.


TBMR Recovery Console
TBMR - Volume Layout
The original and proposed disk volumes are shown below. If required, right-click on a volume to customise the proposed layout.
Stored layout:
Proposed layout:
VPC
CBMR - Disk Partitioning
Yes, partition this disk.
CAUTION: You will lose all the data in this disk!
No, do not partition this disk.
Existing data may be safe.
OK
Cancel
< Back
Next >
Cancel
United Kingdom
http://www.cristie.com
cristie

Any attempt to turn off formatting incorrectly will result in this error.

CBMR - Disk Partitioning
CBMR - Error
This disk must be repartitioned as the existing disk doesn't match the original disk's layout
OK
OK
Cancel

You may also right-click on a partition to allow you to selectively modify the partition parameters or to remove it altogether.


TBMR Recovery Console
TBMR - Volume Layout
The original and proposed disk volumes are shown below. If required, right-click on a volume to customise the proposed layout.
Stored layout:
Proposed layout:
VPC-WIN2K3R2
Disk 0 Size 15.99 GB []
Disk 1 Size 512 MB []
Disk 2 Size 512 MB []
Disk 3 Size 512
VPC-WIN2K3R2
Disk 0 Size 15.99 GB [VMwar
C:[OS], NTFS, Size 4.00
E:[PartitionE], NTFS, Size
Volume / Partition Details
Type : Partition
File System : NTFS
Size in MB : 12284
Label : PartitionE
Mount Details :
Drive Letter : E
Format
OK
Cancel

You may **Modify** the following partition parameters:

- size in MB (only if disk is shown with a)
- label
- format (yes/no)

The screenshot below shows this.



Select **Delete** to remove the partition completely (only if disk is shown with a).

If you attempt to either not format or delete a Windows system partition, an error such as this will be displayed.



At this stage nothing has happened to the disks. Press **Next>** to continue with the recovery.

Proceed With The Recovery

Before continuing with the actual recovery a final warning screen is displayed.

If you are happy with the recovery configuration, press **Finish**. This will commence the actual recovery.

Note: This procedure will completely destroy any existing data on disks selected for format (i.e shown with a). Disks or partitions tagged as *no format* (i.e. shown with a) will however be retained.

Restore from Backupset

If you selected Restore from a backupset then select **Next>.** This will then display the Enter TSM server details:



The system configuration will then be restored from the appropriate backupset which is selected from the next dialog:



The configuration will then be retrieved from the selected backupset. The DR process continues from the Select Filespaces to Restore dialog.


TBMR - Select Filespaces to Restore
The Windows boot and system drives will always be restored. You can select additional drives to be restored by ticking the check box next to the drives.
Drive Letter
Name
File System
C:
\\np-win2k364-vm\c$
NTFS
< Back
Next >
Cancel

Select the filespaces to restore and then the partition layout for the recovering system:


TBMR - Volume Layout
The original and proposed disk volumes are shown below. If required, right-click on a volume to customise the proposed layout.
Stored layout:
Proposed layout:
NP-WIN2K364-VM
Disk 0 Size 8.00 GB []
NP-WIN2K364-VM
Disk 0 Size 8.00 GB [VMware
Icon Help
< Back
Next >
Cancel

Finally select **Finish** and the recovery will then proceed.


TBMR - Finish
Tivoli.
On selecting [Finish], recovery of your system will start. You will be able to monitor the progress in a new window.
< Back
Finish
Cancel

The subsequent recovery continues as described in section Disk Recovery Sequence.

Disk Recovery Sequence

The recovery sequence begins by preparing the disks selected for the recovery.


TBMR Recovery Status
Renaming the computer
Preparing basic disks
INI disk 0, ACT disk 0, Size=16384 MiB, Cyls=2088, TPC=255, SPT=63, BPS=512
Creating basic partitions
Creating any partitions on INI disk 0, ACT disk 0
Created MBR partition (4094 MiB) with drive letter C:, labelled 'OS'
Successfully created all basic disk partitions
Formatting basic partitions
Formatted partition with drive letter C:, labelled 'OS'
Removing any dynamic volumes marked as "failed" by Diskpart
Removing any disks marked as "missing" by Diskpart
Creating partition mount points
Creating volume mount points
Making bootable volumes active
Stopping access to Diskpart
Restore will start shortly in a separate window.
Updating the target registry
Sanity check passed
Copying DisRec.ini to the Windows drive ...Success
Start Dissimilar Hardware. Search new hardware devices in the recovering system.
There are no new devices found in your system.
Recovery finished successfully on 8/5/2010 9:12:07 AM
Close
Abort
http://www.cristie.com

This involves:

- disk mapping original layout to new
- cleaning (removing any existing disk partitions)
- removing any existing dynamic volume databases
- re-creating the partitions
- converting to dynamic volumes if required
- formatting to the required partition type
- create partition/volume mount points
- makes bootable volumes active

The next step is to recover the filespaces to the selected target disks/partitions. A new window appears containing the restore status of recovered files and progress bars indicating how much of the backup has been restored. This display also shows the recovery statistics in terms of time, size and throughput.

Note that the recovery is divided into different phases: SystemState followed by the recovery of each volume filespace selected.



This process may take some minutes if the backups are large. You may select the **Abort** button to terminate the file recovery process, but this may leave the disk or partition in an unpredictable state which may be unusable.

If any errors occur during the recovery, an error message will be shown in the window. Refer to the logs post recovery to establish the cause of any error.

The final steps of the recovery are to:

- run a sanity check to determine if all the expected boot files are present on the boot volume
- run a dissimilar hardware check to determine if new drivers are required for new boot devices

Finally press **Close** to return to the Recovery Console main menu. At this point you may want to view the recovery logs and perhaps copy the logs to a local device or remote share before selecting to reboot. Note that recovery logs are also saved to the recovered system to the TBMR installation sub-folder '*Temp*' (e.g. "C:\Program Files\Cristie\TBMR\Temp").

Disk Scaling

In situations where the target system has fewer or smaller disks than the original system, disk scaling will come into effect. For example,


EBMR Recovery Console
Starts the automatic recovery wizard which will take you through the steps necessary to recover your system.
EBMR - Volume Layout
The original and proposed disk volumes are shown below. If required, right-click on a volume to customise the proposed layout.
Stored layout:
Proposed layout:
VPC-WIN2K3R2
Disk 0 Size 15.99 GB []
Disk 1 Size 512 MB []
Disk 2 Size 512 MB []
Disk 3 Size 512 MB []
VPC-WIN2K3R2
Disk 0 Size 8.00 GB [VMware
Icon Help
< Back
Next >
Cancel
US
Copyright (C) 2006 - 2009 Cristie Software Limited
United Kingdom
http://www.cristie.com
cristie

The above example shows a recovery from an original system with 4 physical disks to a target system with only 1 disk. The target disk is also much smaller than the original disks.

In this case TBMR will select as many disks to recover as possible (in this case only 1 disk - the boot disk). In addition it will scale the partitions down in proportion to their original size and occupancy. This can be complicated by having say mirrored dynamic volumes when the mirror will need to be broken - if only 1 disk exists on the target (or it has been tagged as not to modify).

Note 1: The Volume Layout dialog will only show disks in the left hand panel that can be recovered.

Note 2: During a recovery to a system with larger disks the partition sizes will remain the same as the original by default. However, in this case, it is possible to increase partition size manually during the recovery by right-clicking on the partition icon and selecting Modify.

8.2.3 Start Manual Recovery Sequence

Select this option to commence a manual DR sequence. This option will stop after each step in the DR sequence allowing the DR to be aborted or the step to be repeated with different parameters.

Locate Configuration

The first step of the manual DR sequence is to provide the location of the DR configuration.


TBMR Recovery Console
TBMR - Welcome
Tivoli.
Welcome to the TBMR Manual Recovery Wizard which gives greater control and flexibility in restoring your system.
Select the operation you want to do and select [Next] to proceed.
Access Configuration
Create Partitions and Volumes
Restore Files
Make Bootable
Dissimilar Hardware
< Back
Next >
Cancel
http://www.cristie.com

Press **Next>** to proceed to the first step of the sequence. Press **Cancel** to abort the recovery sequence at this point. You will then be presented with a dialog prompting you to select the type of the TSM restore.


TBMR - Select Restore Type
Please specify the type of restore you wish to perform:
Restore from a TSM node
Restore from a backupset stored on a TSM node
Restore from a backupset stored on a disk or removable media other than tape
< Back
Next >
Cancel

At the moment only restoring from a TSM node or an online backupset is supported. A future release will support restoring from a backupset stored on a disk or removable media.

Press **Next>** to continue to:



Specify the location of the TSM Server and Node used to back up the Client.

Selecting the Point-in-time (PIT) restore mode will allow the system to be recovered to a point closest to the specified date/time. The version of any files restored are closest to but not younger than the specified date/time. If required date is not the current WinPE date, selecting the down-arrow in the day/month field brings up a calendar.


TBMR Recovery Console
TBMR TSM Details
Please enter the TSM Server and Client details below and select [Next] to continue.
TSM Server Details
Server Address :
10.2.1.20
Port :
1500
Backupset Location :
Browse
TSM Client Details
Node Name :
NIGELPTBMR
Node Password :
Point-in-time (PIT) restore
Wednesday, June 24, 2009
10:31:16 AM
June, 2009
Sun Mon Tue Wed Thu Fri Sat
31 1 2 3 4 5 6
7 8 9 10 11 12 13
14 15 16 17 18 19 20
21 22 23 24 25 26 27
28 29 30 1 2 3 4
5 6 7 8 9 10 11
Today: 6/24/2009
< Back
Next >
Cancel

This can be used to scroll the months/years backwards and forwards as necessary. Note, a future date will result in the latest backup being recovered.

The next dialog displayed depends upon whether you selected **restore from node** or restore from **backupset**.

8.3 Restore from Node

Then select **Next>** to continue. If the backup including the TBMR configuration folder TBMRCFG is encrypted, a prompt for the encryption password will be displayed if not held locally:


TBMR Recovery Console
TBMR TSM Details
Please enter the TSM Server and Client details below and select [Next] to continue.
TSM Server Details
Password Request
Data is encrypted using a password. Enter the correct password and press [OK] to proceed. Pressing [Cancel] will abort the operation.
OK
Cancel
Wednesday, June 11, 2008
9:37:11 AM
< Back
Next >
Cancel
http://www.cristie.com

Enter the password used during the backup and press **OK>**.

8.4 Restore from Backupset

The system configuration will be restored from the appropriate backupset which is selected from the next dialog:



Successful extraction of the configuration from the server is confirmed with the following dialog:

Select **Finish** and control returns to the next step in the Manual Recovery sequence.

Create Partition and Volumes

The next step of the manual recovery process is to configure the target disk partitions and volumes.


TBMR Recovery Console
TBMR - Welcome
Tivoli.
Welcome to the TBMR Manual Recovery Wizard which gives greater control and flexibility in restoring your system.
Select the operation you want to do and select [Next] to proceed.
Access Configuration
Create Partitions and Volumes
Restore Files
Make Bootable
Dissimilar Hardware
< Back
Next >
Cancel
http://www.cristie.com

Select **Next>** to display the Volume Layout dialog.


TBMR Recovery Console
TBMR - Volume Layout
The original and proposed disk volumes are shown below. If required, right-click on a volume to customise the proposed layout.
Stored layout:
Proposed layout:
VPC-WIN2K3R2
Disk 0 Size 15.99 GB []
Disk 1 Size 512 MB []
Disk 2 Size 512 MB []
Disk 3 Size 512 MB []
VPC-WIN2K3R2
Disk 0 Size 15.99 GB [VMwar
Disk 1 Size 509 MB [VMware,
Disk 2 Size 509 MB [VMware,
Disk 3 Size 509 MB [VMware,
Icon Help
< Back
Next >
Cancel
http://www.cristie.com

This screen shows the original disk layout against that of the target system. Naturally the target disk layout could be very different to the original. TBMR will attempt to match the disks using its own in-built criteria. Some of the criteria used to judge the match are:

- disk geometry (tracks, cylinders and sectors)
- disk capacity
- if currently formatted, the disk signature

However, it is possible to change the partition size or opt to tag/untag whether or not a partition should be formatted. To do this right click on the the disk icon and the following configuration dialog is displayed.


TBMR Recovery Console
TBMR - Volume Layout
The original and proposed disk volumes are shown below. If required, right-click on a volume to customise the proposed layout.
Stored layout:
Proposed layout:
VPC-WIN2K3R2
Disk 0 Size 15.99 GB []
Disk 1 Size 512 MB []
Disk 2 Size 512 MB []
Disk 3 Size 512
VPC-WIN2K3R2
Disk 0 Size 15.99 GB [VMwar
C:[OS], NTFS, Size 4.00
E:[PartitionE], NTFS, Size
Volume / Partition Details
Type : Partition
File System : NTFS
Size in MB : 12284
Label : PartitionE
Mount Details :
Drive Letter : E
Format
OK
Cancel



The indicator shown next to the disk icon indicates whether that disk will be left intact or not. A red exclamation mark indicates that the disk will be re-partitioned and/or formatted. A green tick indicates that the disk will be left intact.

Disks and partitions are discussed in more detail in the Automatic Recovery - Recovery Details section.

Press **<Back** to return to the previous step, **Finish** to commence the active part of this step or **Cancel** to abort.

If you are happy with the recovery configuration, press **Finish**. This will commence the actual recovery.

Note: This procedure will completely destroy any existing data on the disks selected for recovery. Disks or partitions tagged as *no format* will however be retained.

The **Create Partitions and Volumes** step begins by preparing the disk selected for the recovery.


TBMR Recovery Status
CBMR_DP.DLL 6.3.182 Cristie Disk Partitioner (CDP) created on Jul 28 2010 at 10:27:33
TBMR Console Version 6.3 Build 151
Manual Recovery(Volume Creation) started on 8/5/2010 9:28:15 AM
Restoring Windows Server 2003, Enterprise Edition (build 3790) [Service Pack 1]
Renaming the computer
Preparing basic disks
INI disk 0, ACT disk 0, Size=16384 MiB, Cyls=2088, TPC=255, SPT=63, BPS=512
Creating basic partitions
Creating any partitions on INI disk 0, ACT disk 0
Created MBR partition (4094 MiB) with drive letter C:, labelled 'OS'
Successfully created all basic disk partitions
Formatting basic partitions
Formatted partition with drive letter C:, labelled 'OS'
Removing any dynamic volumes marked as "failed" by Diskpart
Removing any disks marked as "missing" by Diskpart
Creating partition mount points
Creating volume mount points
Making bootable volumes active
Stopping access to Diskpart
The operation(s) finished successfully on 8/5/2010 9:28:46 AM
Close
Abort
http://www.cristie.com

This involves:

- disk mapping original layout to new
- cleaning (removing any existing disk partitions)
- removing any existing dynamic volume databases
- re-creating the partitions
- converting to dynamic volumes if required
- formatting to the required partition type
- create partition/volume mount points
- makes bootable volumes active

Press **Close>** to continue with the recovery.

Restore Files

The next step of the manual recovery process is to restore the DR backup files.


TBMR Recovery Console
TBMR - Welcome
Tivoli.
Welcome to the TBMR Manual Recovery Wizard which gives greater control and flexibility in restoring your system.
Select the operation you want to do and select [Next] to proceed.
Access Configuration
Create Partitions and Volumes
Restore Files
Make Bootable
Dissimilar Hardware
< Back
Next >
Cancel
http://www.cristie.com

Press Next> to identify the TSM filespaces that should be recovered. Note that the *SystemState filespace* will always be recovered by default.



Press **Next>** to commence the restore of the TSM filespaces to their target disks/partitions.

Finally, a new window appears containing the restore status of recovered files and progress bars indicating how much of the backup has been restored. This display also shows the recovery statistics in terms of time, size and throughput.

Note that the recovery is divided into different phases: SystemState followed by the recovery of each volume filespace selected.



This process may take some minutes if the backups are large. You may select the **Abort** button to terminate the file recovery process, but this may leave the disk or partition in an unpredictable state which may be unusable.

If any errors occur during the recovery, an error message will be shown in the window. Refer to the logs post recovery to establish the cause of any error. When the restore files step completes the following dialog is displayed.

Select **Finish** and control returns to the next step in the Manual Recovery sequence.

Make Bootable

The next step in the manual recovery sequence is to make the original disk 'bootable'. This involves re-creating the MBR of the boot disk and modifying the registry with the new disk GUID.


TBMR Recovery Console
TBMR - Welcome
Tivoli.
Welcome to the TBMR Manual Recovery Wizard which gives greater control and flexibility in restoring your system.
Select the operation you want to do and select [Next] to proceed.
Access Configuration
Create Partitions and Volumes
Restore Files
Make Bootable
Dissimilar Hardware
< Back
Next >
Cancel
http://www.cristie.com

Press **Next>** to commence the make bootable step..

A new dialog window opens summarising the success or failure of the operation..


TBMR Recovery Status
CBMR_DP.DLL 6.3.182 Cristie Disk Partitioner (CDP) created on Jul 28 2010 at 10:27:33
TBMR Console Version 6.3 Build 151
Manual Recovery(Make Bootable) started on 8/5/2010 9:39:37 AM
Updating the target registry
Sanity check passed
Copying DisRec.ini to the Windows drive ...Success
The operation(s) finished successfully on 8/5/2010 9:39:38 AM
Close
Abort
http://www.cristie.com

Press **Close** to complete the step and return to the Manual Recovery Wizard.

Dissimilar Hardware

The final step in the manual DR sequence is to check if the recovery is to dissimilar hardware.

This is determined by comparing the drivers currently in use by Windows PE and the drivers listed in the recovered machine's registry.

The step first prompts for what driver types should be checked. By default only Mass Storage (disk) and network devices are checked.


TBMR Recovery Console
TBMR - Types of Drivers
Specify if all Windows drivers will be checked and loaded:
Load all types of drivers
Note: it is generally only necessary to inject drivers for mass storage and some network devices. Drivers for other device types (such as chipset, CPU type etc.) can be safely ignored and left for standard Windows Plug-and-Play processing on reboot. However if you wish to load all types of PCI devices, tick the following box.
< Back
Next >
Cancel
http://www.cristie.com

Press **Next>** to continue. For recovery to similar hardware no new devices will be found and this will be confirmed by this dialog:



Press **Finish** to complete the manual recovery sequence.

8.4.1 Tools

There are a few tools that can assist with the recovery process. They are all collected under this command button.

The options available are:

- Load a driver
- Configure the network
- Dissimilar Hardware Wizard
- Start VNC
- Set trace levels
- Advanced options

Selecting **Configure the network** will start the Cristie Network Configurator tool. This provides extensive facilities to configure network during the DR process.

The Dissimilar Hardware Wizard will allow drivers to be injected into the recovered system when the target hardware has different devices from the original (e.g. RAID controllers). Normally this will be done automatically as part of the DR sequence and will not need to be run manually.

Start VNC will run a VNC server within the PE environment so allowing external VNC clients to remotely connect during the DR session. The start process will provide you with the current IP address of the PE environment which you will need to specify in the VNC client. Note that the VNC connection is also password protected.The VNC feature is intended for diagnosing DR problems under the guidance of Cristie Support who will provide the password upon request.

Set trace levels allows the DR log file trace to be increased or decreased as required.



It is recommended that the trace levels are only changed when advised to do so by Cristie Support staff. This is because they could have a severe impact upon the performance of the backup restore process.

Advanced options should only be selected when advised to do so by Cristie Support staff.



Cristie Network Configurator Tool

This is a very powerful tool that provides extensive facilities to configure the network during the recovery process. It offers the following features:

- supports multiple NICs
- configure individual NIC parameters for duplex mode and link speed
- the ability to select DHCP allocated or static IP addresses
- the ability to setup DNS and WINS server IP addresses
- the ability to setup the Network Identification of the recovering system.
- allow file shares to be set on the recovering system.
- map/unmap network drives.

Configure NIC Parameters

It is possible to change both the link speed and duplex mode for any NIC detected on the recovering target system. Select the desired NIC (there could be more than one) from the drop down box and then select **Update...**.



The resulting display offers numerous NIC properties that can be changed. This property list is dependent upon the NIC - i.e. not all properties will be available for all NICs.


NVIDIA nForce Networking Controller Properties
Advanced
The following properties are available for this network adapter. Click the property you want to change on the left, and then select its value on the right.
Property:
Value:
Flow Control
Interrupt Moderation
IP Checksum Offload
Jumbo Packet
Large Send Offload version 1 (IPv4)
Large Send Offload version 2 (IPv4)
Large Send Offload version 2 (IPv6)
Network Address
Priority & VLAN
Speed & duplex settings
TCP Checksum Offload (IPv4)
TCP Checksum Offload (IPv6)
UDP Checksum Offload (IPv4)
UDP Checksum Offload (IPv6)
Auto Negotiation
OK
Cancel

To change the NIC speed or duplex setting, select the corresponding *Property* from the dialog and then select the required value from the *Value* drop down box as shown below:


NVIDIA nForce Networking Controller Properties
Advanced
The following properties are available for this network adapter. Click the property you want to change on the left, and then select its value on the right.
Property:
Flow Control
Interrupt Moderation
IP Checksum Offload
Jumbo Packet
Large Send Offload version 1 (IPv4)
Large Send Offload version 2 (IPv4)
Large Send Offload version 2 (IPv6)
Network Address
Priority & VLAN
Speed & duplex settings
TCP Checksum Offload (IPv4)
TCP Checksum Offload (IPv6)
UDP Checksum Offload (IPv4)
UDP Checksum Offload (IPv6)
Value:
Auto Negotiation
10 Mbps Half Duplex
10 Mpbs Full Duplex
100 Mbps Full Duplex
100 Mbps Half Duplex
Auto Negotiation
OK
Cancel

Again note that the speed/duplex settings available are NIC dependent. *Auto Negotiation* is generally the NIC default setting.

Other NIC properties may be changed as required.

Assign Static or DHCP IP Settings

Normally the WinPE 2 DR environment will start with DHCP enabled and active. However, if a static IP is required use the Use the following IP addresse option to manually configure.

First ensure the desired network adapter is selected from the drop down list. If a static IP address is to be applied select the Use the following IP address button. This will automatically deselect the default DHCP option and allow the static IP parameters to be defined.



Set the new IP address, subnet mask and gateway IP address. The **More** button will allow the system to have more than one static IP addresses.

Click on **Apply** to confirm the settings for the selected adapter.

This feature will also allow the DHCP lease to be released or renewed, as required.

Map a Network Drive

In order to simplify access to network resources, the Network Configurator allows you to map a network drive to a network share.

Start the Cristie Network Configurator from the Tools menu and select the **Map Network Drives** tab.



Select the drive letter that you wish to allocate from the **Drive** drop-down box and type in the share name that you wish to associate with it. Also specify the network credentials to be used to access the share. Press **Map Drive** to confirm the share operation. If successful the share will be added to the **Unmap a network drive** drop down list (see below).



Disconnect Network Drives

If you need to disconnect a mapped drive for any reason, this option allows you to do this. Just select the drive that you wish to disconnect from the **Unmap a network drive** drop down list and then click **Unmap Drive**.



The mapped drive is removed from the list to confirm the operation.

Setup DNS Servers

DNS server IP addresses are automatically set when the WinPE 2 DR environment boots. However, options are provided to allow DNS server IP addresses to be manually set if required. Note WINS servers are not currently supported by this tool.



Select the **Use the following DNS Server address** button and enter the new DNS IP server address. If required, select the **More** button to add several DNS IP addresses. Press **Apply** to activate the new address.

Setup Network Identification

It is possible to setup the Network Identification of the recovering system. This allows the WinPE 2 hostname and Primary DNS suffix to be changed during a DR session. These details are transient and only apply while the WinPE 2 DR session is running. They are not applied to the recovering system when it reboots after the DR session.



Enter the new **Computer Name** and press **Set** to confirm the change.



Display MAC Address

It is possible to display the local MAC address of the recovering system. Select the MAC Address 

button at the top of the Main menu dialog.



Note it is not possible to change the MAC address.

Save/Restore NIC Configuration Parameters

During a WinPE 2 DR session it is possible to save the current network configuration to a local file. Select the Save

button to do this. Enter a suitable filename. This file is transient and will only exist for the current DR session.



This avoids the need to manually re-enter parameters when you are trying out different combinations of NIC parameters. Use the Load

button to restore saved configurations.

Dissimilar Hardware Wizard

A restore to dissimilar hardware is normally detected during the Automatic or Manual DR sequence and drivers will be injected automatically at the end of the restore sequence if a source location has been provided. However, if this process has failed for some reason or additional drivers are required to be injected into the recovering machine then this Dissimilar Hardware Wizard tool is provided.

Note it is only necessary to load the drivers for the hard disk, NIC and rarely the HAL. Drivers for the hard disks and NIC can be determined by Plug-and-Play (PnP) and may be readily identified. However changes required in the CPU model via a change in HAL, cannot yet be determined by PnP; these need to be loaded manually.

If you wish to scan for just Mass Storage and Network devices (the minimum required to boot a dissimilar system) select **Next>** to continue to the next step of the Wizard. This is the recommended option. Under the guidance of Cristie Support you may be asked to scan for all devices. In this case tick the "Scan for all devices" box before selecting **Next>**.


DHW - Welcome
Welcome to Dissimilar Hardware Wizard. This will take you through the steps to install the necessary drivers for your new hardware. You may need the installation media from the hardware manufacturer.
Scan for only network and mass storage devices (Recommended)
Scan for all devices (Select only when asked by Cristie support)
cristie
Dissimilar Hardware Wizard - Version 6.3 Build 83
Copyright (C) 2003-2010 Cristie Software Limited
United Kingdom
http://www.cristie.com
< Back
Next >
Cancel

Select the Install Drivers using Plug-and-Play option.


DHW - Select An Option
Select one of the following options and select [Next]
Install Drivers using Plug-and-Play
Manually Install Drivers
Advanced Options
< Back
Next >
Cancel

Install Drivers using Plug-and-Play

The window appears empty to start with. The set of drivers located on the recovery CD is the default choice, but in practice they should not be used. Instead change the driver search path to where you have actually located your drivers (for example, to a network share or another CD) with the **Change** command button.



In the example above the driver search path is changed to the VMware drivers on the WinPE boot CD.

Begin the PnP driver detection by clicking **Start**.



The process checks the devices that it can detect and when it finds one that does not have a driver loaded, it will offer to install it. The example below shows an LSI SCSI device being detected.


Found a new hardware!
CBMR found a new hardware in your system.
SCSI Controller
A matching driver "X:\VMDRIVERS\32-BIT\LSI_SCSI.INF" is found. Select [Install] to install this driver. Selecting [Install All] will install the matching drivers for newly found devices without prompting.
Stop Searching
Driver Path : X:\VMDRIVERS\32-BIT
Change Driver Path
Search Again
Install
Install All
Skip
Cancel

If you are satisfied that the found driver path is correct, click on **Install** and the driver will be installed. The device scan will continue and may find for example other mass storage or network devices. Follow the steps above to install as shown in the example above.

Drivers are usually .sys files. The .inf files define which driver files need to be loaded for a given device. You may need to confirm the location of the driver files for each device, or possibly find the path where they are stored. When you have the correct path, click on **OK** and the wizard will look for more.

Once all of the drivers of the detected devices have been processed, the wizard will indicate that the installation has finished. Click on **Finish** to proceed.


DHW - PnP Manager
1. Select the folder where you have stored your Windows drivers
Driver Path : X:\VMDRIVERS\32-BIT
Change
2. Press the [Start] button to start scanning.
Start
The following devices were found by the PnP manager:
Bus Class Description
PCI SCSIAdapter SCSI Controller
PCI Net Intel(R) PRO/1000 MT Network Connection
Installing drivers for the newly found devices
Installing driver for [SCSI Controller] ... Installed
Installing driver for [Intel(R) PRO/1000 MT Network Connection] ... Skipped
Finished installing drivers for the newly found devices.
< Back
Finish
Cancel

Manual Installation

Normally you would only manually install a driver for a CPU/HAL change. Select *Manually Install Drivers* from the option menu


DHW - Select An Option
Select one of the following options and select [Next]
Install Drivers using Plug-and-Play
Manually Install Drivers
Advanced Options
< Back
Next >
Cancel

Then select **Next>**.



Select **Browse...** to locate the driver or HAL file you need by browsing to the appropriate folder that holds the .inf file. If you need to load the driver from another machine, then you can browse to a share on that machine and then to the appropriate folder.



Here we are selecting the VMware SCSI controller driver.



The wizard allows you to select drivers that are grouped by manufacturer. Select the actual driver that you wish to install and click **Next>**.



After you confirm the selection, the wizard determines which files need to be installed. You are given the opportunity to change the location from which they are loaded if required..

When the drivers have been installed, the wizard allows you to go back to install another device driver or finish the process.


DHW - Finish
The selected driver is successfully installed. If you want to install more drivers select the [Back] button and select the new drivers.
If you are finished with the drivers, select [Finish] and the wizard will exit. You may now reboot the just recovering server for the changes to take effect.
< Back
Finish
Cancel

Load a Driver

Allows a new mass storage or Network card driver to be loaded into the WinPE 2 environment. Use this when WinPE 2 does not have a built-in driver for your hardware.

For example if the DR environment does not show any disks to be recovered you can inject a new mass storage device driver for the device and retry the DR wizard.

You will be prompted for the location of the driver INF file:


CBMR - Dynamic Driver Loading
Specify the location where the driver installation (.INF) file can be found .
Browse
Load
Cancel

The INF file and other associated driver files (such as the .SYS file) can be located on a CD, USB device or a network share. The following confirmation dialog is displayed if the driver is loaded successfully:



8.4.2 Show Log and Error Reports

This main menu option allows the log files produced during the recovery to be viewed using notepad. Normally viewing this information is only required to diagnose a problem with the recovery.


TBMR Recovery Console
Starts the automatic recovery wizard which will take you
TBMR - Logfiles
Highlight a file and select [View] to view its contents.. Select [Close] to close this dialog.
Icon Name
Date
Time
Size
setupapi.log 05/08/10 10:55:28 99 KB
CBAC_trace.log 05/08/10 10:38:48 13 KB
dsmerror.log 05/08/10 10:38:46 5 KB
CDP_trace.log 05/08/10 10:39:40 207 KB
CDP_dump1.log 05/08/10 10:28:16 13 KB
bmr_status.log 05/08/10 11:02:32 3 KB
CBAC_dump.log 05/08/10 10:31:48 572
CDP_dump2.log 05/08/10 10:39:40 13 KB
Network.log 05/08/10 10:39:40 3 KB
dhw_log.log 05/08/10 10:55:28 6 KB
View
Close
Copyright (C) 2006 - 2010 Cristie Software Limited
United Kingdom
http://www.cristie.com
cristie

bmr_status.log - restored disk and registry configuration log, e.g. disks/partitions created summary etc.

cbac_dump.log - contains a summary of the TSM client/server versions and node details.

cbac_trace.log - contains a detailed summary of the TSM client/server communications. Used by Cristie Support for diagnosing TSM interface problems.

cdp_dump1.log - contains general information regarding the system BIOS, disk configuration and timezone details of the original system.

cdp_dump2.log- contains general information regarding the system BIOS, disk configuration and timezone details of the target system.

cdp_trace.log - contains a detailed summary of how the partitions were restored. Used by Cristie Support for diagnosing disk configuration problems.

dhw.log - contains a summary of Dissimilar Hardware Wizard activities. Used by Cristie Support for diagnosing new driver problems.

dsmerror.log - TSM interface log information

network.log - contains NIC hardware summary, current network configuration (e.g. IP address, gateway IP address etc.) and routing table.

setupapi.log - contains a summary of the Plug and Play devices detected by WinPE as it boots. Used by Cristie Support for diagnosing WinPE driver problems.

8.4.3 Copy Log and Error Report Files

Since all log and error files generated during the recovery are only transitory (i.e. they are lost as soon as the Windows PE environment exits), this option allows you to copy the to a local device or remote network share for permanent record. Use the Cristie Network Configurator Tool , http://www. to setup a network share.


TBMR Recovery Console
Starts the automatic recovery wizard which will take you through the steps necessary to recover your system.
Starts the manual recovery wizard which will let you do individual recovery steps.
TBMR - Copy Logfiles
Specify the location where the logfiles need to be copied.
Copy logfiles to the following location:
A:\
Browse
OK
Cancel
GMT Daylight Time - 5/30/2008 10:44:27 AM
US
TBMR Recovery Console Version 5.3.1 Build 93
Copyright (C) 2006 - 2008 Cristie Software Limited
United Kingdom
http://www.cristie.com
cristie

The example shows files being copied to a local floppy drive.

Note that the logs are automatically written back to the recovered system after a successful DR. They are saved to the TBMR installation sub-folder *Temp*.

8.4.4 Close Recovery Console and Reboot


TBMR Recovery Console
Starts the automatic recovery wizard which will take you through the steps necessary to recover your system.
Starts the manual recovery wizard which will let you do individual recovery steps.
Lets you run various tools relevant to the recovery.
TBMR - Warning
Exiting this program will restart your computer. Do you really want to exit?
Yes
No
Will close this console and reboot the system.
GMT Daylight Time - 8/5/2010 11:20:27 AM
US
TBMR Recovery Console Version 6.3 Build 151
Copyright (C) 2006 - 2010 Cristie Software Limited
United Kingdom
http://www.cristie.com
cristie

After a successful recovery, select this option to exit the Windows PE environment and boot the recovered system.

Press **Yes** to the restart confirmation warning or **No** to continue running the DR console. If you choose to reboot the recovered Windows system will start.


TBMR - Complete
Tivoli.
Thank you for choosing TBMR as your backup and disaster recovery software.
TBMR has finished recovery from the recent disaster.
OK

The above dialog is displayed when the recovered system re-starts and shows the successful completion of the Disaster Recovery.

9 Index

6

64-bit Versions of Windows XP, Vista, Windows 7, 2003 and 2008 • 6

A

Assign Static or DHCP IP Settings • 43

B

Backup Process • 2
Backupset Support • 11
Booting the DR Console • 12

C

Close Recovery Console and Reboot • 60
Configure NIC Parameters • 41
Confirm Volume Layout • 18, 33
Context • 2
Copy Log and Error Report Files • 60
Create Partition and Volumes • 31
Creating the Configuration Information • 4
Cristie Network Configurator Tool • 40, 60

D

Disconnect Network Drives • 47
Disk Recovery Sequence • 25
Disk Scaling • 27
Display MAC Address • 51
Dissimilar Hardware • 38
Dissimilar Hardware Wizard • 52

E

Encrypted Backups • 8

I

Image Backups • 10

L

Load a Driver • 58
Locate Configuration • 27

M

Make Bootable • 37
Map a Network Drive • 44

O

Overview • 2

P

Prerequisites • 2
Proceed With The Recovery • 22

R

Recovery Process • 3
Restore Files • 35
Restore from Backupset • 23
Restore from Node • 16
Restoring your System • 2, 12

S

Save/Restore NIC Configuration Parameters • 52
Select Filespaces To Restore • 18
Setup DNS Servers • 48
Setup Network Identification • 49
Show Log and Error Reports • 59
Specify TSM Details and Recovery Date/Time • 16
Start Automatic Recovery Wizard • 15
Start Manual Recovery Sequence • 27

T

TBMR Recovery Console Main Menu • 14
The TBMR Create Configuration Tool • 2, 4
Tools • 39

U

Using a TSM Backup for Disaster Recovery • 2, 7

W

WinPE 2 Based TBMR Recovery Console • 13